

AKZO™ Data Interface

Introduction


CCC ONE® allows you to enable Data Interfaces with external vendor applications. To do this, you must set up the Data Interface and accept the EULA for that vendor.

This job aid describes how to set up a Data Interface for AKZO™.

Add Data Interface



Note: Only one Data Interface can be set up per machine with CCC ONE® installed. If you are an MSO user with access to multiple locations, you will need to setup the Data Interface for each Location on separate machines.

Use the following steps to enable the AKZO™ Data Interface:

Step	Action
1	<p>Go to Configure and select Machine Settings.</p>  <p>The screenshot shows a software interface with a 'Configure' dropdown menu open. The menu items are: My Account (with an external link icon), Profiles, Machine Settings (highlighted with an orange border), Employees, Teams, Security Roles, Work Hours, Accounting Connections, Checklists (with an external link icon), CCC Secure Share™ (with an external link icon), and Grow My Network (with an external link icon). The 'Configure' and 'Tools' buttons are visible at the top of the menu.</p>

AKZO™ Data Interface, continued



Add Data Interface, continued

Step	Action
2	<p>Under Import/Export select Data Interfaces.</p>  <p>The screenshot shows a tree view under 'Machine Settings'. The 'Import/Export' folder is expanded, and the 'Data Interfaces' option is highlighted with a red box. Other options visible include 'Directories', 'EMS Extract Preferences', 'File Export', and 'File Import'.</p>
3	<p>Click Add on the toolbar.</p>  <p>The screenshot shows the 'Machine Settings' window with the 'Data Interfaces' dialog box open. The 'Add' button on the dialog's toolbar is highlighted with a red box. The dialog has a table with columns for 'Interface', 'Export', 'Directory', and 'EULA'. The 'Add' button is located to the left of the 'Remove' button.</p>

Continued on next page

AKZO™ Data Interface, continued


Add Data Interface, continued

Step	Action
4	<p>Select AKZO Mixit Pro and click OK.</p>  <p>The EULA will display.</p>
5	<p>Check the I Agree checkbox and click OK.</p> 

AKZO™ Data Interface, continued

Setup AKZO Data Interface

Use the following steps to configure the newly added Data Interface:



Step	Action
1	If an MSO, select the Location for the Interface.
2	Choose an Export Frequency . Default is Every 1 Hour .
3	Enter or browse to the Directory Path for the exported file.
4	Click OK to save your selections.

Note: Once set up, the computer **must** be logged into CCC ONE to export the XML files using the settings you selected.